

LineLidar class

Generated by Doxygen 1.9.1

1 Python3 LineLidar class	1
1.1 Description	1
1.2 Notes	1
2 Module Index	3
2.1 Modules	3
3 Namespace Index	5
3.1 Packages	5
4 Hierarchical Index	7
4.1 Class Hierarchy	7
5 Class Index	9
5.1 Class List	9
6 Module Documentation	11
6.1 Base classes	11
6.1.1 Detailed Description	11
6.2 Enums	11
6.2.1 Detailed Description	11
6.3 Main classes	11
6.3.1 Detailed Description	11
6.4 Default parameters	11
6.5 Routines	11
7 Namespace Documentation	13
7.1 linelidarclass Namespace Reference	13
7.2 linelidarclass.default Namespace Reference	13
7.3 linelidarclass.linelidar Namespace Reference	14
7.3.1 Function Documentation	14
7.3.1.1 discover()	14
8 Class Documentation	15
8.1 _LLchr Class Reference	15
8.1.1 Detailed Description	15
8.1.2 Constructor & Destructor Documentation	15
8.1.2.1 __init__()	15
8.1.3 Member Function Documentation	16
8.1.3.1 __eq__()	16
8.1.3.2 __hash__()	16
8.1.3.3 __setattr__()	16
8.2 _LLcmd Class Reference	17
8.2.1 Detailed Description	17
8.3 _LLintEnum Class Reference	18

8.3.1 Detailed Description	18
8.3.2 Constructor & Destructor Documentation	18
8.3.2.1 __init__()	18
8.3.3 Member Function Documentation	19
8.3.3.1 __eq__()	19
8.3.3.2 __hash__()	19
8.3.3.3 __setattr__()	19
8.4 _LLsrv Class Reference	20
8.4.1 Detailed Description	20
8.5 _LLsta Class Reference	21
8.5.1 Detailed Description	21
8.6 ipaddress Class Reference	21
8.6.1 Detailed Description	22
8.7 LineLidar Class Reference	22
8.7.1 Detailed Description	23
8.7.2 Constructor & Destructor Documentation	24
8.7.2.1 __init__()	24
8.7.3 Member Function Documentation	25
8.7.3.1 __decode_msg()	25
8.7.3.2 __encode_cmd()	25
8.7.3.3 __highlighted_bytes()	26
8.7.3.4 __recv_ssh_line()	26
8.7.3.5 __retry_cmd()	27
8.7.3.6 __windows_reader_thread()	27
8.7.3.7 __get_cmd_response()	28
8.7.3.8 __recv_msg()	29
8.7.3.9 __send_cmd()	30
8.7.3.10 __send_data()	30
8.7.3.11 disable_all_notifications()	31
8.7.3.12 disable_notification()	31
8.7.3.13 enable_notification()	32
8.7.3.14 get_notification()	32
8.7.3.15 open()	33
8.7.3.16 read_chr()	34
8.7.3.17 report_zero_results()	34
8.7.3.18 reset()	35
8.7.3.19 restore_srv()	35
8.7.3.20 save_srv()	36
8.7.3.21 set_clean_state()	36
8.7.3.22 set_notification()	37
8.7.3.23 set_sampling_rate()	37
8.7.3.24 stop_sampling()	38

8.7.3.25 wait_device_quiet()	38
8.7.3.26 write_chr()	39
8.7.4 Member Data Documentation	39
8.7.4.1 int	39
8.8 LLchr Class Reference	40
8.8.1 Detailed Description	40
8.8.2 Notes	40
8.8.3 Member Data Documentation	40
8.8.3.1 AMPLITUDE_THRESHOLD	40
8.8.3.2 CALIBRATED_ANGLES	41
8.8.3.3 DEFAULT_NETWORK	41
8.8.3.4 FW_VERSION	41
8.8.3.5 MAC	41
8.8.3.6 MAX_ANGLE	42
8.8.3.7 MAX_DISTANCE	42
8.8.3.8 MEASURING_RATE	42
8.8.3.9 MIN_ANGLE	42
8.8.3.10 MIN_DISTANCE	43
8.8.3.11 NB_PEAKS	43
8.8.3.12 NETWORK	43
8.8.3.13 RANGE	43
8.8.3.14 REPORT_ZERO_RESULTS	44
8.8.3.15 RESET_DEVICE	44
8.8.3.16 SERIAL_NUMBER	44
8.8.3.17 TEMPERATURE	44
8.8.3.18 TIME	45
8.8.3.19 TRIGGER_DIVISION	45
8.8.3.20 TRIGGER_SOURCE	45
8.8.3.21 TRIGGER_TYPE	45
8.9 LLcmd Class Reference	46
8.9.1 Detailed Description	46
8.10 LLresponse Class Reference	46
8.10.1 Detailed Description	47
8.10.2 Member Function Documentation	47
8.10.2.1 __repr__()	47
8.10.3 Member Data Documentation	47
8.10.3.1 reset	47
8.11 LLsrv Class Reference	48
8.11.1 Detailed Description	48
8.11.2 Notes	48
8.12 LLsta Class Reference	48
8.12.1 Detailed Description	48

8.13 macaddress Class Reference	48
8.13.1 Detailed Description	49
Index	51

Chapter 1

Python3 LineLidar class

1.1 Description

Low-level class to communicate with a LineLidar device in Python

1.2 Notes

Copyright 2023 (c) Noptel Oy, Oulu Finland

Tested on:

- Linux
- Windows

Authors: PCo

Chapter 2

Module Index

2.1 Modules

Here is a list of all modules:

Base classes	11
Enums	11
Main classes	11
Default parameters	11
Routines	11

Chapter 3

Namespace Index

3.1 Packages

Here are the packages with brief descriptions (if available):

linelidarclass		
LineLidar Low-level communication class	13
linelidarclass.default		
LineLidar Low-level communication class	13
linelidarclass.linelidar		
LineLidar Low-level communication class	14

Chapter 4

Hierarchical Index

4.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

_LLchr	15
_LLintEnum	18
_LLcmd	17
_LLsrv	20
_LLsta	21
ipaddress	21
LineLidar	22
LLchr	40
LLcmd	46
LLresponse	46
LLsrv	48
LLsta	48
macaddress	48

Chapter 5

Class Index

5.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

_LLchr	15
_LLcmd	LineLidar command enum element	17
_LLintEnum	18
_LLsrv	LineLidar service enum element	20
_LLsta	LineLidar status code enum element	21
ipaddress	Simple IPv4 address class	21
LineLidar	Main LineLidar class	22
LLchr	Characteristics	40
LLcmd	Commands / command responses	46
LLresponse	Decoded response class	46
LLsrv	Services	48
LLsta	Status codes	48
macaddress	Simple MAC address class	48

Chapter 6

Module Documentation

6.1 Base classes

Classes

- class [ipaddress](#)
- class [macaddress](#)

6.1.1 Detailed Description

6.2 Enums

Classes

- class [LLcmd](#)
- class [LLsrv](#)
- class [LLchr](#)
- class [LLsta](#)

6.2.1 Detailed Description

6.3 Main classes

Classes

- class [LLresponse](#)
- class [LineLidar](#)

6.3.1 Detailed Description

Type definitions.

Main classes

6.4 Default parameters

6.5 Routines

Chapter 7

Namespace Documentation

7.1 linelidarclass Namespace Reference

Namespaces

- [default](#)
- [linelidar](#)

Classes

- class [ipaddress](#)
- class [macaddress](#)
- class [_LLintEnum](#)
- class [_LLcmd](#)
- class [_LLsrv](#)
- class [_LLsta](#)
- class [_LLchr](#)
- class [LLcmd](#)
- class [LLsrv](#)
- class [LLchr](#)
- class [LLsta](#)
- class [LLresponse](#)

Variables

- list [__all__](#) = ["default", "linelidar"]

7.2 linelidarclass.default Namespace Reference

Variables

- int [_ll_default_port](#) = 9907
- float [_ll_default_udp_timeout](#) = 1.5
- int [_ll_default_ssh_timeout](#) = 5
- int [_ll_default_reboot_timeout](#) = 5
- int [_ll_default_retries](#) = 1
- int [_ll_default_sent_cmds_log_depth](#) = 16
- string [_ll_default_ssh_python_path](#) = "python"

7.3 linelidarclass.linelidar Namespace Reference

Classes

- class [LineLidar](#)

Functions

- List[str] [discover](#) (Optional[str] network=None, Optional[int] port=_ll_default_port, Optional[str] sshcmd=None, Optional[str] sshpypath=None, int retries=None, bool debug=False, Optional[float] timeout=None)

7.3.1 Function Documentation

7.3.1.1 discover()

```
List[str] linelidarclass.linelidar.discover (
    Optional[str] network = None,
    Optional[int] port = _ll_default_port,
    Optional[str] sshcmd = None,
    Optional[str] sshpypath = None,
    int retries = None,
    bool debug = False,
    Optional[float] timeout = None )
```

Discover LineLidar devices on a network.

Parameters

<i>network</i>	Network / netmask to discover devices on, in xx.xx.xx.xx/mm format, or None to discover on all interfaces
<i>port</i>	Port of devices to discover
<i>sshcmd</i>	If specified, ssh command to log into a shell account to use the host as a relay to talk to the LineLidar . Works with a Linux or Windows host with sshd and Python 2 or 3 installed.
<i>sshpypath</i>	Path of the Python executable on the SSH relay host
<i>retries</i>	How many more times the discovery packet should be sent for redundancy
<i>debug</i>	Enable or disable debugging messages
<i>timeout</i>	Communication timeout in seconds

Returns

Broadcast a read request for the NETWORK characteristic, wait for replies and return the list of addresses of the devices that replied.

Definition at line 2089 of file linelidar.py.

Chapter 8

Class Documentation

8.1 `_LLchr` Class Reference

Public Member Functions

- None `__init__` (`_LLchr` self, str name, Tuple[`_LLsrv`, int] value)
- bool `__eq__` (`_LLchr` self, object other)
- None `__setattr__` (`_LLchr` self, str attr, val)
- int `__hash__` (`_LLchr` self)

Private Attributes

- `_hash`

8.1.1 Detailed Description

Pseudo-enum element to store a (`_LLsrv`, int) tuple describing a characteristic

```
@ingroup BaseClasses
```

Definition at line 229 of file `__init__.py`.

8.1.2 Constructor & Destructor Documentation

8.1.2.1 `__init__()`

```
None __init__ (
    _LLchr self,
    str name,
    Tuple[_LLsrv, int] value )
```

Initialize the enum element

Definition at line 244 of file `__init__.py`.

8.1.3 Member Function Documentation

8.1.3.1 `__eq__()`

```
bool __eq__ (
    _LLchr self,
    object other )
```

`__eq__` method to compare two enum elements

Definition at line 257 of file `__init__.py`.

8.1.3.2 `__hash__()`

```
int __hash__ (
    _LLchr self )
```

`__hash__` method

Definition at line 278 of file `__init__.py`.

8.1.3.3 `__setattr__()`

```
None __setattr__ (
    _LLchr self,
    str attr,
    val )
```

Disabled setter, as enums are immutable


Definition at line 267 of file `__init__.py`.

The documentation for this class was generated from the following file:


- `linelidarclass/__init__.py`

8.2 _LLcmd Class Reference

Inheritance diagram for _LLcmd:



Collaboration diagram for _LLcmd:



Additional Inherited Members

8.2.1 Detailed Description


Definition at line 208 of file `__init__.py`.

The documentation for this class was generated from the following file:

- `linelidarclass/__init__.py`

8.3 _LLintEnum Class Reference

Inheritance diagram for _LLintEnum:



Public Member Functions

- None `__init__` (`_LLintEnum` self, str name, int value)
- bool `__eq__` (`_LLintEnum` self, object other)
- None `__setattr__` (`_LLintEnum` self, str attr, val)
- int `__hash__` (`_LLintEnum` self)

Public Attributes

- **value**

8.3.1 Detailed Description

Pseudo-enum element to store an integer value

@ingroup BaseClasses

Definition at line 153 of file `__init__.py`.

8.3.2 Constructor & Destructor Documentation

8.3.2.1 `__init__()`

```

None __init__ (
    _LLintEnum self,
    str name,
    int value )

```

Initialize the enum element

Definition at line 166 of file `__init__.py`.

8.3.3 Member Function Documentation

8.3.3.1 `__eq__()`

```
bool __eq__ (
    _LLintEnum self,
    object other )
```

`__eq__` method to compare two enum elements

Definition at line 178 of file `__init__.py`.

8.3.3.2 `__hash__()`

```
int __hash__ (
    _LLintEnum self )
```

`__hash__` method

Definition at line 199 of file `__init__.py`.

8.3.3.3 `__setattr__()`

```
None __setattr__ (
    _LLintEnum self,
    str attr,
    val )
```

Disabled setter, as enums are immutable


Definition at line 188 of file `__init__.py`.

The documentation for this class was generated from the following file:


- `linelidarclass/__init__.py`

8.4 _LLsrv Class Reference

Inheritance diagram for _LLsrv:



Collaboration diagram for _LLsrv:



Additional Inherited Members

8.4.1 Detailed Description


Definition at line 215 of file `__init__.py`.

The documentation for this class was generated from the following file:


- `linelidarclass/__init__.py`

8.5 _LLsta Class Reference

Inheritance diagram for _LLsta:



Collaboration diagram for _LLsta:



Additional Inherited Members

8.5.1 Detailed Description

Definition at line 222 of file `__init__.py`.

The documentation for this class was generated from the following file:

- `linelidarclass/__init__.py`

8.6 ipaddress Class Reference

Public Member Functions

- `None __init__ (ipaddress self, Union[str, bytes] addr)`
- `bool __eq__ (ipaddress self, object other)`
- `str __repr__ (ipaddress self)`

Public Attributes

- [ip](#)

8.6.1 Detailed Description

Definition at line 42 of file `__init__.py`.

The documentation for this class was generated from the following file:

- `linelidarclass/__init__.py`

8.7 LineLidar Class Reference

Public Member Functions

- None `__init__` ([LineLidar](#) self, Optional[str] addr=None, Optional[int] port=None, Optional[str] sshcmd=None, Optional[str] sshpypath=None, Optional[int] sent_cmds_log_depth=None, [int retries](#)=None, bool [set_clean_state](#)=True, bool autostop_ranging=True, bool debug=False, Optional[float] timeout=None)
- [LineLidar](#) `__enter__` ([LineLidar](#) self)
- None `__exit__` ([LineLidar](#) self, Optional[Type[BaseException]] exc_type, Optional[BaseException] exc_value, Optional[TracebackType] exc_traceback)
- None `__del__` ([LineLidar](#) self)
- Union[socket.socket, Tuple[subprocess.Popen, Optional[multiprocessing.queues.Queue]]] `open` ([LineLidar](#) self, str addr, Optional[int] port=None, Optional[str] sshcmd=None, Optional[str] sshpypath=None, Optional[int] sent_cmds_log_depth=None, [int retries](#)=None, bool [set_clean_state](#)=True, bool autostop_ranging=True, Optional[float] timeout=None)
- None `close` ([LineLidar](#) self)
- LLresponse `read_chr` ([LineLidar](#) self, _LLchr char, [int retries](#)=None, bool exc_on_nok=True, Optional[float] timeout=None)
- LLresponse `write_chr` ([LineLidar](#) self, _LLchr char, [int retries](#)=None, bool exc_on_nok=True, Optional[float] timeout=None, **_CHR_ARGS_TYPE kwargs)
- LLresponse `set_notification` ([LineLidar](#) self, _LLchr char, bool enabled, [int retries](#)=None, bool exc_on_nok=True, Optional[float] timeout=None)
- LLresponse `enable_notification` ([LineLidar](#) self, _LLchr char, [int retries](#)=None, bool exc_on_nok=True, Optional[float] timeout=None)
- LLresponse `disable_notification` ([LineLidar](#) self, _LLchr char, [int retries](#)=None, bool exc_on_nok=True, Optional[float] timeout=None)
- LLresponse `disable_all_notifications` ([LineLidar](#) self, bool incl_restricted=False, [int retries](#)=None, bool exc_on_nok=True, Optional[float] timeout=None)
- LLresponse `report_zero_results` ([LineLidar](#) self, bool on, [int retries](#)=None, bool exc_on_nok=True, Optional[float] timeout=None)
- LLresponse `set_sampling_rate` ([LineLidar](#) self, [int](#) frequency, [int retries](#)=None, bool exc_on_nok=True, Optional[float] timeout=None)
- LLresponse `stop_sampling` ([LineLidar](#) self, [int retries](#)=None, bool exc_on_nok=True, Optional[float] timeout=None)
- LLresponse `save_srv` ([LineLidar](#) self, _LLsrv srv, [int retries](#)=None, bool exc_on_nok=True, Optional[float] timeout=None)
- LLresponse `restore_srv` ([LineLidar](#) self, _LLsrv srv, [int retries](#)=None, bool exc_on_nok=True, Optional[float] timeout=None)
- None `flush_notifications` ([LineLidar](#) self)
- LLresponse `get_notification` ([LineLidar](#) self, Union[List[_LLchr], Tuple[_LLchr], None] chrmask=None, Optional[float] timeout=None)
- None `wait_device_quiet` ([LineLidar](#) self, Optional[float] timeout=None)
- None `set_clean_state` ([LineLidar](#) self, bool incl_restricted=False, [int retries](#)=None, Optional[float] timeout=None)
- None `reset` ([LineLidar](#) self, bool reconnect=True, Optional[float] reconnect_timeout=None, [int retries](#)=None, bool exc_on_nok=True, Optional[float] timeout=None)

Public Attributes

- [retries](#)
- [notifications](#)

Static Public Attributes

- [int](#)

Private Member Functions

- [str __highlighted_bytes](#) ([LineLidar](#) self, bytes b, Optional[[int](#)] start=None, Optional[[int](#)] end=None)
- [None __send_data](#) ([LineLidar](#) self, Union[bytes, List[bytes]] data)
- [Tuple\[bytes, Optional\[str\]\] __encode_cmd](#) ([LineLidar](#) self, [int](#) msgid, [_LLcmd](#) cmd, Union[[_LLsrv](#), [_LLchr](#)] chr_or_srv, *bool args, **_CHR_ARGS_TYPE kwargs)
- [int __send_cmd](#) ([LineLidar](#) self, [_LLcmd](#) cmd, Union[[_LLsrv](#), [_LLchr](#)] chr_or_srv, *bool args, **_CHR_ARGS_TYPE kwargs)
- [None __windows_reader_thread](#) ([LineLidar](#) self, IO fd, multiprocessing.queues.Queue queue)
- [str __recv_ssh_line](#) ([LineLidar](#) self, Optional[[float](#)] timeout=None)
- [LLresponse __decode_msg](#) ([LineLidar](#) self, bytes msg)
- [LLresponse __recv_msg](#) ([LineLidar](#) self, Optional[[float](#)] timeout=None)
- [LLresponse __get_cmd_response](#) ([LineLidar](#) self, bool exc_on_cmd=True, bool exc_on_msgid=True, bool exc_on_chr=True, bool exc_on_nok=True, bool ignore_sent_cmds_log=False, Optional[[float](#)] timeout=None)
- [LLresponse __retry_cmd](#) ([LineLidar](#) self, [_LLcmd](#) cmd, Union[[_LLsrv](#), [_LLchr](#)] chr_or_srv, [int](#) retries=None, bool exc_on_nok=True, Optional[[float](#)] timeout=None, *bool args, **_CHR_ARGS_TYPE kwargs)

Private Attributes

- [__debug](#)
- [__default_timeout](#)
- [__timeout](#)
- [__autostop_ranging](#)
- [__is_ranging](#)
- [__ssh_recvbuf](#)
- [__netmask](#)
- [__addrport](#)
- [__sent_cmds_log_depth](#)
- [__sent_cmds_log](#)
- [__msgid](#)

Static Private Attributes

- [__socket](#) = None
- [__sshproc](#) = None
- [__sshproc_win_stdout](#) = None
- [__win_reader_thread](#) = None

8.7.1 Detailed Description

Definition at line 183 of file `linelidar.py`.

8.7.2 Constructor & Destructor Documentation

8.7.2.1 `__init__()`

```
None __init__ (
    LineLidar self,
    Optional[str] addr = None,
    Optional[int] port = None,
    Optional[str] sshcmd = None,
    Optional[str] sshpypath = None,
    Optional[int] sent_cmds_log_depth = None,
    int retries = None,
    bool set_clean_state = True,
    bool autostop_ranging = True,
    bool debug = False,
    Optional[float] timeout = None )
```

SSH receive buffer.

Default communication timeout in seconds

Current communication timeout in seconds

Whether to automatically stop ranging upon closing the device

Whether the device is currently ranging

last sent message ID

Sent commands log depth

Sent commands log

How many times a failed command should be retried for fault-tolerance

Notifications stack

Debugging messages toggle

Enum-by-value mappings

`__init__` method

Parameters

<i>addr</i>	IP address of the device. If unspecified, the device is not automatically opened.
<i>port</i>	Port of the device (if the device is automatically opened)
<i>sshcmd</i>	If specified, ssh command to log into a shell account to use the host as a relay to talk to the LineLidar (if the device is automatically opened). Works with a Linux or Windows host with sshd and Python 2 or 3 installed.
<i>sshpypath</i>	Path of the Python executable on the SSH relay host (if the device is automatically opened)
<i>sent_cmds_log_depth</i>	Number of sent commands tracked, to ignore out-of-order responses that have already generated a timeout (if the device is automatically opened). Set to 1 to disable filtering out out-of-order UDP packets.
<i>retries</i>	How many times a failed command should be retried (if the device is automatically opened)
<i>set_clean_state</i>	Set device in a known, stopped state after opening (if the device is automatically

Definition at line 266 of file linelidar.py.

8.7.3 Member Function Documentation

8.7.3.1 __decode_msg()

```
LLresponse __decode_msg (
    LineLidar self,
    bytes msg ) [private]
```

Decode a message from the LineLidar.

Parameters

<i>msg</i>	Packet to decode
------------	------------------

Returns

Received response

Definition at line 1152 of file linelidar.py.

8.7.3.2 __encode_cmd()

```
Tuple[bytes, Optional[str]] __encode_cmd (
    LineLidar self,
    int msgid,
    _LLcmd cmd,
    Union[_LLsrv, _LLchr] chr_or_srv,
    *bool args,
    **_CHR_ARGS_TYPE kwargs ) [private]
```

Encode a LineLidar command.

Parameters

<i>msgid</i>	Message ID
<i>cmd</i>	Command to encode
<i>chr_or_srv</i>	Characteristic or service
<i>args</i>	Positional arguments (here, only True or False allowed - see below)
<i>kwargs</i>	Keyworded arguments (see below)

If the command is SAVE_SERVICE or RESTORE_SERVICE, pass a service ([_LLsrv](#)) in chr_or_srv. Otherwise pass a characteristic ([_LLchr](#))

If the command is SET_NOTIFICATION, pass a single argument True or False to enable or disable notification - e.g. `_encode_cmd(LLcmd.SET_NOTIFICATION, LLchr.TEMPERATURE, True)`

If the command is WRITE, pass the relevant parameters as keyworded arguments - e.g. `_encode_cmd(LLcmd.WRITE, LLchr.MIN_DISTANCE, distance = 3.5)`

Returns

(Encoded command, optional debug message)

Definition at line 687 of file linelidar.py.

8.7.3.3 __highlighted_bytes()

```
str __highlighted_bytes (
    LineLidar self,
    bytes b,
    Optional[int] start = None,
    Optional[int] end = None ) [private]
```

Generate a printable byte sequence in hex with a slice of it highlighted.

Parameters

<i>b</i>	Byte sequence
<i>start</i>	Start of the byte sequence slice to highlight
<i>end</i>	End of the byte sequence slice to highlight

Returns

Printable hex byte sequence

Definition at line 354 of file linelidar.py.

8.7.3.4 __recv_ssh_line()

```
str __recv_ssh_line (
    LineLidar self,
    Optional[float] timeout = None ) [private]
```

Get a line of text from the SSH client.

Parameters

<i>timeout</i>	Communication timeout in seconds
----------------	----------------------------------

Returns

Received text line

Definition at line 1061 of file linelidar.py.

8.7.3.5 __retry_cmd()

```
LLresponse __retry_cmd (
    LineLidar self,
    _LLcmd cmd,
    Union[_LLsrv, _LLchr] chr_or_srv,
    int retries = None,
    bool exc_on_nok = True,
    Optional[float] timeout = None,
    *bool args,
    **_CHR_ARGS_TYPE kwargs ) [private]
```

Try to send a command to the device and get a response from it.

If the response times out, retry sending the command and getting a new response until the number of allowed retries runs out.

Parameters

<i>cmd</i>	Command to send
<i>chr_or_srv</i>	Characteristic or service
<i>retries</i>	How many times a failed command should be retried
<i>exc_on_nok</i>	Raise an exception on response not OK
<i>timeout</i>	Communication timeout in seconds
<i>args</i>	Positional arguments for <code>_send_cmd</code>
<i>kwargs</i>	Keyworded arguments for <code>_send_cmd</code>

Returns

Response to the command

Definition at line 1591 of file linelidar.py.

8.7.3.6 __windows_reader_thread()

```
None __windows_reader_thread (
    LineLidar self,
    IO fd,
    multiprocessing.queues.Queue queue ) [private]
```

Windows-only blocking file reader thread.

This thread reads data from a blocking file and transfer the data to a queue, which in turn can be read with a timeout.

This workaround is required because Windows doesn't provide `select()` on file descriptors.

Definition at line 1014 of file linelidar.py.

8.7.3.7 `_get_cmd_response()`

```
LLresponse _get_cmd_response (
    LineLidar self,
    bool exc_on_cmd = True,
    bool exc_on_msgid = True,
    bool exc_on_chr = True,
    bool exc_on_nok = True,
    bool ignore_sent_cmds_log = False,
    Optional[float] timeout = None ) [private]
```

Get a response to the latest command (i.e.

not a notification).

Parameters

<i>exc_on_cmd</i>	Raise an exception if the response's command doesn't match that of the last sent command
<i>exc_on_msgid</i>	Raise an exception if the response's message ID doesn't match that of the last sent command
<i>exc_on_chr</i>	Raise an exception if the response's characteristic doesn't match that of the last sent command in responses to READ commands
<i>exc_on_nok</i>	Raise an exception on response not OK (see below)
<i>ignore_sent_cmds_log</i>	If asserted, incoming messages will not be checked against older entries in the sent commands log to catch out-of-order responses, and the last sent command will not be removed from the log
<i>timeout</i>	Communication timeout in seconds

if `ignore_sent_cmds_log` isn't asserted, if a response to a command is received and its message ID, command and service or characteristic match one of the older entries in the sent commands log, the response is considered an out-of-order message, the corresponding entry is removed from the sent commands log and the response is silently discarded.

After discarding out-of-order messages, if either the message's command, message ID or characteristic (in the case of response to a READ command) don't match the last sent command's and either `exc_on_cmd`, `exc_on_msgid` or `exc_on_chr` are asserted (default), an exception is raised.

if `ignore_sent_cmds_log` isn't asserted and the response matches the last sent command, it is removed from the log.

If `exc_on_nok` is asserted (default), an exception is raised when the response's status is not OK.

If a NOTIFICATION is received, it is pushed into the notifications stack and the function keeps on waiting for a response to a command.

Returns

Received response

Definition at line 1425 of file `linelidar.py`.

8.7.3.8 _recv_msg()

```
LLresponse _recv_msg (
    LineLidar self,
    Optional[float] timeout = None ) [private]
```

Get a message from the LineLidar.

Parameters

<i>timeout</i>	Communication timeout in seconds
----------------	----------------------------------

Returns

Received response

Definition at line 1312 of file linelidar.py.

8.7.3.9 `_send_cmd()`

```
int _send_cmd (
    LineLidar self,
    _LLcmd cmd,
    Union[_LLsrv, _LLchr] chr_or_srv,
    *bool args,
    **_CHR_ARGS_TYPE kwargs ) [private]
```

Send a command to the device.

Parameters

<i>cmd</i>	Command to send
<i>chr_or_srv</i>	Characteristic or service
<i>args</i>	Positional arguments (here, only True or False allowed - see below)
<i>kwargs</i>	Keyworded arguments (see below)

If the command is `SAVE_SERVICE` or `RESTORE_SERVICE`, pass a service (`_LLsrv`) in `chr_or_srv`. Otherwise pass a characteristic (`_LLchr`)

If the command is `SET_NOTIFICATION`, pass a single argument True or False to enable or disable notification - e.g. `_send_cmd(LLcmd.SET_NOTIFICATION, LLchr.TEMPERATURE, True)`

If the command is `WRITE`, pass the relevant parameters as keyworded arguments - e.g. `_send_cmd(LLcmd.WRITE, LLchr.MIN_DISTANCE, distance = 3.5)`

Returns

Sent message ID

Definition at line 931 of file linelidar.py.

8.7.3.10 `_send_data()`

```
None _send_data (
    LineLidar self,
    Union[bytes, List[bytes]] data ) [private]
```

Send data to the LineLidar.

Parameters

<i>data</i>	Data to send in the form of a byte array or a list of byte arrays
-------------	---

If the data is sent to the [LineLidar](#) directly, the data in the form of a byte array is sent.

If the data is sent to the [LineLidar](#) through a SSH relay, if the data is in the form of a byte array, it is first encapsulated in a list. Then the list of byte array(s) is pickled, base-64 encoded and sent to the SSH relay stub.

Definition at line 646 of file linelidar.py.

8.7.3.11 disable_all_notifications()

```
LLresponse disable_all_notifications (
    LineLidar self,
    bool    incl_restricted = False,
    int     retries = None,
    bool    exc_on_nok = True,
    Optional[float] timeout = None )
```

Disable notification on all characteristics that support it.

Parameters

<i>incl_restricted</i>	Also disable notification on characteristics where notifications are restricted
<i>retries</i>	How many times a failed command should be retried
<i>exc_on_nok</i>	Raise an exception on response not OK (see below)
<i>timeout</i>	Communication timeout in seconds

Definition at line 1769 of file linelidar.py.

8.7.3.12 disable_notification()

```
LLresponse disable_notification (
    LineLidar self,
    _LLchr char,
    int     retries = None,
    bool    exc_on_nok = True,
    Optional[float] timeout = None )
```

Disable notification on a characteristic.

Parameters

<i>char</i>	Characteristic to disable notification on
<i>retries</i>	How many times a failed command should be retried
<i>exc_on_nok</i>	Raise an exception on response not OK (see below)
<i>timeout</i>	Communication timeout in seconds

If `exc_on_nok` is asserted (default), an exception is raised when the response's status is not OK.

Returns

SET_NOTIFICATION command response

Definition at line 1743 of file `linelidar.py`.

8.7.3.13 `enable_notification()`

```
LLresponse enable_notification (
    LineLidar self,
    _LLchr char,
    int retries = None,
    bool exc_on_nok = True,
    Optional[float] timeout = None )
```

Enable notification on a characteristic.

Parameters

<i>char</i>	Characteristic to enable notification on
<i>retries</i>	How many times a failed command should be retried
<i>exc_on_nok</i>	Raise an exception on response not OK (see below)
<i>timeout</i>	Communication timeout in seconds

If `exc_on_nok` is asserted (default), an exception is raised when the response's status is not OK.

Returns

SET_NOTIFICATION command response

Definition at line 1718 of file `linelidar.py`.

8.7.3.14 `get_notification()`

```
LLresponse get_notification (
    LineLidar self,
    Union[List[_LLchr], Tuple[_LLchr], None] chrmask = None,
    Optional[float] timeout = None )
```

Get a notification, either from the notifications stack, or receive it from the device if the stack is empty.

Parameters

<i>chrmask</i>	List of expected notification characteristics (see below)
<i>timeout</i>	Communication timeout in seconds

If a message other than a notification is received from the device (i.e. a response to a command), an exception is raised.

If a list of characteristics is specified in chrmask and the notification's characteristic isn't in that list, an exception is raised.

Returns

Received notification.

Definition at line 1933 of file linelidar.py.

8.7.3.15 open()

```
Union[socket.socket,Tuple[subprocess.Popen, Optional[ multiprocessing.queues.Queue]]] open (
    LineLidar self,
    str addr,
    Optional[int] port = None,
    Optional[str] sshcmd = None,
    Optional[str] sshpypath = None,
    Optional[int] sent_cmds_log_depth = None,
    int retries = None,
    bool set_clean_state = True,
    bool autostop_ranging = True,
    Optional[float] timeout = None )
```

Open communication with a LineLidar.

Parameters

<i>addr</i>	IP address of the device
<i>port</i>	Port of the device
<i>sshcmd</i>	If specified, ssh command to log into a shell account to use the host as a relay to talk to the LineLidar . Works with a Linux or Windows host with sshd and Python 2 or 3 installed.
<i>sshpypath</i>	Path of the Python executable on the SSH relay host
<i>sent_cmds_log_depth</i>	Number of sent commands tracked, to ignore out-of-order responses that have already generated a timeout. Set to 1 to disable filtering out out-of-order UDP packets.
<i>retries</i>	How many times a failed command should be retried
<i>set_clean_state</i>	Set device in a known, stopped state after opening
<i>autostop_ranging</i>	Enable or disable automatically stopping ranging upon closing the device
<i>timeout</i>	Communication timeout in seconds

Returns

Open UDP socket if the communication with the device is direct, or the tuple (open SSH client process, Windows-only stdout queue) if the communication with the device goes through an SSH relay host. On Linux machines, the Windows-only stdout queue is always None. On Windows machine, it is a multiprocessing.Queue() object from which the SSH process' stdout can be read in non-blocking mode instead of the process' stdout handle, which is always blocking.

Definition at line 379 of file linelidar.py.

8.7.3.16 read_chr()

```
LLresponse read_chr (
    LineLidar self,
    _LLchr char,
    int retries = None,
    bool exc_on_nok = True,
    Optional[float] timeout = None )
```

Read a characteristic.

Parameters

<i>char</i>	Characteristic to read
<i>retries</i>	How many times a failed command should be retried
<i>exc_on_nok</i>	Raise an exception on response not OK (see below)
<i>timeout</i>	Communication timeout in seconds

If *exc_on_nok* is asserted (default), an exception is raised when the response's status is not OK.

Returns

READ command response.

Definition at line 1640 of file linelidar.py.

8.7.3.17 report_zero_results()

```
LLresponse report_zero_results (
    LineLidar self,
    bool on,
    int retries = None,
    bool exc_on_nok = True,
    Optional[float] timeout = None )
```

Enable or disable zero results reporting.

Parameters

<i>on</i>	Whether to report zero results
<i>retries</i>	How many times a failed command should be retried
<i>exc_on_nok</i>	Raise an exception on response not OK (see below)
<i>timeout</i>	Communication timeout in seconds

If `exc_on_nok` is asserted (default), an exception is raised when the response's status is not OK.

Returns

WRITE command response

Definition at line 1806 of file `linelidar.py`.

8.7.3.18 reset()

```
None reset (
    LineLidar self,
    bool reconnect = True,
    Optional[float] reconnect_timeout = None,
    int retries = None,
    bool exc_on_nok = True,
    Optional[float] timeout = None )
```

Soft-reset the device.

Parameters

<i>reconnect</i>	Attempt to reconnect the device after reset
<i>reconnect_timeout</i>	Timeout in seconds when attempting to reconnect
<i>retries</i>	How many times a failed command should be retried. Only applies if <code>reconnect</code> is False.
<i>exc_on_nok</i>	Raise an exception on response not OK (see below). Only applies if <code>reconnect</code> is False.
<i>timeout</i>	Communication timeout in seconds. Only applies if <code>reconnect</code> is False.

If `exc_on_nok` is asserted (default), an exception is raised when the response's status is not OK.

Definition at line 2027 of file `linelidar.py`.

8.7.3.19 restore_srv()

```
LLresponse restore_srv (
    LineLidar self,
    _LLsrv srv,
    int retries = None,
    bool exc_on_nok = True,
    Optional[float] timeout = None )
```

Restore a service from non-volatile memory.

Parameters

<i>srv</i>	Service to restore from non-volatile memory
<i>retries</i>	How many times a failed command should be retried
<i>exc_on_nok</i>	Raise an exception on response not OK (see below)
<i>timeout</i>	Communication timeout in seconds

If `exc_on_nok` is asserted (default), an exception is raised when the response's status is not OK.

Returns

RESTORE_SERVICE command response

Definition at line 1900 of file `linelidar.py`.

8.7.3.20 `save_srv()`

```
LLresponse save_srv (
    LineLidar self,
    _LLsrv srv,
    int retries = None,
    bool exc_on_nok = True,
    Optional[float] timeout = None )
```

Save a service to non-volatile memory.

Parameters

<i>srv</i>	Service to save to non-volatile memory
<i>retries</i>	How many times a failed command should be retried
<i>exc_on_nok</i>	Raise an exception on response not OK (see below)
<i>timeout</i>	Communication timeout in seconds

If `exc_on_nok` is asserted (default), an exception is raised when the response's status is not OK.

Returns

SAVE_SERVICE command response

Definition at line 1876 of file `linelidar.py`.

8.7.3.21 `set_clean_state()`

```
None set_clean_state (
    LineLidar self,
    bool incl_restricted = False,
    int retries = None,
    Optional[float] timeout = None )
```

Stop any active ranging, disable all notifications and flush the notifications stack, so that the device is left in a known, stopped state.

Parameters

<i>incl_restricted</i>	Also disable notification on characteristics where notifications are restricted
<i>retries</i>	How many times a failed command should be retried
<i>timeout</i>	Communication timeout in seconds

Definition at line 2000 of file linelidar.py.

8.7.3.22 set_notification()

```
LLresponse set_notification (
    LineLidar self,
    _LLchr char,
    bool enabled,
    int retries = None,
    bool exc_on_nok = True,
    Optional[float] timeout = None )
```

Enable or disable notification on a characteristic.

Parameters

<i>char</i>	Characteristic to enable or disable notification on
<i>enabled</i>	Whether notification is enabled
<i>retries</i>	How many times a failed command should be retried
<i>exc_on_nok</i>	Raise an exception on response not OK (see below)
<i>timeout</i>	Communication timeout in seconds

If *exc_on_nok* is asserted (default), an exception is raised when the response's status is not OK.

Returns

SET_NOTIFICATION command response

Definition at line 1692 of file linelidar.py.

8.7.3.23 set_sampling_rate()

```
LLresponse set_sampling_rate (
    LineLidar self,
    int frequency,
    int retries = None,
    bool exc_on_nok = True,
    Optional[float] timeout = None )
```

Set the sampling rate.

Parameters

<i>frequency</i>	Sampling frequency
<i>retries</i>	How many times a failed command should be retried
<i>exc_on_nok</i>	Raise an exception on response not OK (see below)
<i>timeout</i>	Communication timeout in seconds

If *exc_on_nok* is asserted (default), an exception is raised when the response's status is not OK.

Returns

WRITE command response

Definition at line 1830 of file `linelidar.py`.

8.7.3.24 stop_sampling()

```
LLresponse stop_sampling (
    LineLidar self,
    int retries = None,
    bool exc_on_nok = True,
    Optional[float] timeout = None )
```

Stop sampling.

Parameters

<i>retries</i>	How many times a failed command should be retried
<i>exc_on_nok</i>	Raise an exception on response not OK (see below)
<i>timeout</i>	Communication timeout in seconds

If *exc_on_nok* is asserted (default), an exception is raised when the response's status is not OK.

Returns

WRITE command response

Definition at line 1854 of file `linelidar.py`.

8.7.3.25 wait_device_quiet()

```
None wait_device_quiet (
    LineLidar self,
    Optional[float] timeout = None )
```

Wait until the device becomes silent.

Parameters

<i>timeout</i>	Communication timeout in seconds
----------------	----------------------------------

Definition at line 1980 of file linelidar.py.

8.7.3.26 write_chr()

```
LLresponse write_chr (
    LineLidar self,
    _LLchr char,
    int retries = None,
    bool exc_on_nok = True,
    Optional[float] timeout = None,
    **_CHR_ARGS_TYPE kwargs )
```

Write a characteristic.

Parameters

<i>char</i>	Characteristic to write
<i>retries</i>	How many times a failed command should be retried
<i>exc_on_nok</i>	Raise an exception on response not OK (see below)
<i>timeout</i>	Communication timeout in seconds
<i>kwargs</i>	Keyworded arguments (see below)

Pass the relevant parameters as keyworded arguments - e.g. `write_chr(LLchr.MIN_DISTANCE, distance = 3.5)`

If `exc_on_nok` is asserted (default), an exception is raised when the response's status is not OK.

Returns

WRITE command response

Definition at line 1663 of file linelidar.py.

8.7.4 Member Data Documentation

8.7.4.1 int

```
int [static]
```

Address and port of the device or network.

Netmask to filter incoming UDP replies by IP - Default: /32 (single host)

Definition at line 194 of file linelidar.py.

The documentation for this class was generated from the following file:

- linelidarclass/linelidar.py

8.8 LLchr Class Reference

Static Public Attributes

- [SERIAL_NUMBER](#)
- [FW_VERSION](#)
- [NETWORK](#)
- [TIME](#)
- [TEMPERATURE](#)
- [MAC](#)
- [DEFAULT_NETWORK](#)
- [MIN_DISTANCE](#)
- [MAX_DISTANCE](#)
- [AMPLITUDE_THRESHOLD](#)
- [MIN_ANGLE](#)
- [MAX_ANGLE](#)
- [TRIGGER_SOURCE](#)
- [NB_PEAKS](#)
- [REPORT_ZERO_RESULTS](#)
- [TRIGGER_TYPE](#)
- [TRIGGER_DIVISION](#)
- [CALIBRATED_ANGLES](#)
- [RANGE](#)
- [MEASURING_RATE](#)
- [RESET_DEVICE](#)

8.8.1 Detailed Description

8.8.2 Notes

Underscore in a name indicates a private characteristic

Definition at line 356 of file `__init__.py`.

8.8.3 Member Data Documentation

8.8.3.1 AMPLITUDE_THRESHOLD

```
AMPLITUDE_THRESHOLD    [static]
```

Initial value:

```
= _LLchr("AMPLITUDE_THRESHOLD",  
        (LLsrv.DEVICE_CONFIG, 0x0005))
```

Amplitude threshold.

Definition at line 416 of file `__init__.py`.

8.8.3.2 CALIBRATED_ANGLES

CALIBRATED_ANGLES [static]

Initial value:

```
= _LLchr("CALIBRATED_ANGLES",  
        (LLsrv.HW_CONFIG, 0x0008))
```

Calibrated angles table.

Definition at line 458 of file `__init__.py`.

8.8.3.3 DEFAULT_NETWORK

DEFAULT_NETWORK [static]

Initial value:

```
= _LLchr("DEFAULT_NETWORK",  
        (LLsrv.DEVICE_INFO, 0x0013))
```

Default network.

Definition at line 399 of file `__init__.py`.

8.8.3.4 FW_VERSION

FW_VERSION [static]

Initial value:

```
= _LLchr("FW_VERSION",  
        (LLsrv.DEVICE_INFO, 0x0003))
```

Firmware version.

Definition at line 374 of file `__init__.py`.

8.8.3.5 MAC

MAC [static]

Initial value:

```
= _LLchr("MAC",  
        (LLsrv.DEVICE_INFO, 0x000b))
```

MAC address.

Definition at line 394 of file `__init__.py`.

8.8.3.6 MAX_ANGLE

```
MAX_ANGLE    [static]
```

Initial value:

```
=    _LLchr("MAX_ANGLE",  
            (LLsrv.DEVICE_CONFIG, 0x000b))
```

Maximum angle.

Definition at line 426 of file `__init__.py`.

8.8.3.7 MAX_DISTANCE

```
MAX_DISTANCE    [static]
```

Initial value:

```
=    _LLchr("MAX_DISTANCE",  
            (LLsrv.DEVICE_CONFIG, 0x0003))
```

Maximum ranging distance.

Definition at line 411 of file `__init__.py`.

8.8.3.8 MEASURING_RATE

```
MEASURING_RATE    [static]
```

Initial value:

```
=    _LLchr("MEASURING_RATE",  
            (LLsrv.RESULTS, 0x0008))
```

Measuring rate.

Definition at line 470 of file `__init__.py`.

8.8.3.9 MIN_ANGLE

```
MIN_ANGLE    [static]
```

Initial value:

```
=    _LLchr("MIN_ANGLE",  
            (LLsrv.DEVICE_CONFIG, 0x000a))
```

Minimum angle.

Definition at line 421 of file `__init__.py`.

8.8.3.10 MIN_DISTANCE

MIN_DISTANCE [static]

Initial value:

```
= _LLchr("MIN_DISTANCE",  
        (LLsrv.DEVICE_CONFIG, 0x0002))
```

Minimum ranging distance.

Definition at line 406 of file `__init__.py`.

8.8.3.11 NB_PEAKS

NB_PEAKS [static]

Initial value:

```
= _LLchr("NB_PEAKS",  
        (LLsrv.DEVICE_CONFIG, 0x000d))
```

Number of peaks.

Definition at line 436 of file `__init__.py`.

8.8.3.12 NETWORK

NETWORK [static]

Initial value:

```
= _LLchr("NETWORK",  
        (LLsrv.DEVICE_INFO, 0x0004))
```

NETWORK: network settings.

Definition at line 379 of file `__init__.py`.

8.8.3.13 RANGE

RANGE [static]

Initial value:

```
= _LLchr("RANGE",  
        (LLsrv.RESULTS, 0x0003))
```

Rangefinding results.

Definition at line 465 of file `__init__.py`.

8.8.3.14 REPORT_ZERO_RESULTS

```
REPORT_ZERO_RESULTS  [static]
```

Initial value:

```
=  _LLchr("REPORT_ZERO_RESULTS",  
         (LLsrv.DEVICE_CONFIG, 0x000e))
```

Report zero results toggle.

Definition at line 441 of file `__init__.py`.

8.8.3.15 RESET_DEVICE

```
RESET_DEVICE  [static]
```

Initial value:

```
=  _LLchr("RESET_DEVICE",  
         (LLsrv.DEBUG, 0x0007))
```

Reset device.

Definition at line 477 of file `__init__.py`.

8.8.3.16 SERIAL_NUMBER

```
SERIAL_NUMBER  [static]
```

Initial value:

```
=  _LLchr("SERIAL_NUMBER",  
         (LLsrv.DEVICE_INFO, 0x0002))
```

Serial number.

Definition at line 369 of file `__init__.py`.

8.8.3.17 TEMPERATURE

```
TEMPERATURE  [static]
```

Initial value:

```
=  _LLchr("TEMPERATURE",  
         (LLsrv.DEVICE_INFO, 0x0007))
```

Temperature of the device.

Definition at line 389 of file `__init__.py`.

8.8.3.18 TIME

TIME [static]

Initial value:

```
= _LLchr("TIME",  
        (LLsrv.DEVICE_INFO, 0x0005))
```

TIME: current time.

Definition at line 384 of file `__init__.py`.

8.8.3.19 TRIGGER_DIVISION

TRIGGER_DIVISION [static]

Initial value:

```
= _LLchr("TRIGGER_DIVISION",  
        (LLsrv.DEVICE_CONFIG, 0x0010))
```

Trigger division.

Definition at line 451 of file `__init__.py`.

8.8.3.20 TRIGGER_SOURCE

TRIGGER_SOURCE [static]

Initial value:

```
= _LLchr("TRIGGER_SOURCE",  
        (LLsrv.DEVICE_CONFIG, 0x000c))
```

Trigger source.

Definition at line 431 of file `__init__.py`.

8.8.3.21 TRIGGER_TYPE

TRIGGER_TYPE [static]

Initial value:

```
= _LLchr("TRIGGER_TYPE",  
        (LLsrv.DEVICE_CONFIG, 0x000f))
```

Trigger type.

Definition at line 446 of file `__init__.py`.

The documentation for this class was generated from the following file:

- `linelidarclass/__init__.py`

8.9 LLcmd Class Reference

Static Public Attributes

- `ERROR` = `_LLcmd("ERROR", 0x0000)`
- `READ` = `_LLcmd("READ", 0x0001)`
- `WRITE` = `_LLcmd("WRITE", 0x0002)`
- `NOTIFICATION` = `_LLcmd("NOTIFICATION", 0x0005)`
- `SET_NOTIFICATION` = `_LLcmd("SET_NOTIFICATION", 0x0006)`
- `SAVE_SERVICE` = `_LLcmd("SAVE_SERVICE", 0x0007)`
- `RESTORE_SERVICE` = `_LLcmd("RESTORE_SERVICE", 0x0008)`

8.9.1 Detailed Description

Definition at line 289 of file `__init__.py`.

The documentation for this class was generated from the following file:

- `linelidarclass/__init__.py`

8.10 LLresponse Class Reference

Public Member Functions

- `None __init__ (LLresponse self, Optional[_LLcmd] cmd=None, Optional[int] msgid=None, Optional[_LLsta] status=None, Optional[_LLchr] char=None, Optional[datetime] recv_local_timestamp=None)`
- `str __repr__ (LLresponse self)`

Public Attributes

- `recv_local_timestamp`
- `cmd`
- `msgid`
- `status`
- `char`
- `value`
- `major`
- `minor`
- `bugfix`
- `addr`
- `defaultgw`
- `netmask`
- `port`
- `time`
- `temperature`
- `mac`
- `distance`
- `angle`
- `source`

- [type](#)
- [div](#)
- [frequency](#)
- [threshold](#)
- [angles](#)
- [peaks](#)
- [timestamp](#)
- [measurementid](#)
- [nbresults](#)
- [reset](#)

8.10.1 Detailed Description

Definition at line 517 of file `__init__.py`.

8.10.2 Member Function Documentation

8.10.2.1 `__repr__()`

```
str __repr__ (
    LLresponse self )
```

Generate a printable description of the response.

Returns

printable response

Definition at line 691 of file `__init__.py`.

8.10.3 Member Data Documentation

8.10.3.1 `reset`

```
reset
```

Attribute present in notifications or read command responses for characteristic RANGE.

Attribute present in read command responses for characteristic RESET

Definition at line 687 of file `__init__.py`.

The documentation for this class was generated from the following file:

- `linelidarclass/__init__.py`

8.11 LLsrv Class Reference

Static Public Attributes

- `DEVICE_INFO` = `_LLsrv("DEVICE_INFO", 0x0001)`
- `DEVICE_CONFIG` = `_LLsrv("DEVICE_CONFIG", 0x0002)`
- `HW_CONFIG` = `_LLsrv("HW_CONFIG", 0x0003)`
- `RESULTS` = `_LLsrv("RESULTS", 0x0004)`
- `DEBUG` = `_LLsrv("DEBUG", 0x0005)`

8.11.1 Detailed Description

8.11.2 Notes

Underscore in a name indicates a private service

Definition at line 325 of file `__init__.py`.

The documentation for this class was generated from the following file:

- `linelidarclass/__init__.py`

8.12 LLsta Class Reference

Static Public Attributes

- `OK` = `_LLsta("OK", 0x0000)`
- `CHAR_DECODING_FAILED` = `_LLsta("CHAR_DECODING_FAILED", 0x0001)`
- `CHAR_OUT_OF_RANGE` = `_LLsta("CHAR_OUT_OF_RANGE", 0x0002)`
- `PROCEDURE_IN_PROGRESS` = `_LLsta("PROCEDURE_IN_PROGRESS", 0x0003)`
- `PROCEDURE_FAILED` = `_LLsta("PROCEDURE_FAILED", 0x0004)`
- `NOT_ALLOWED` = `_LLsta("NOT_ALLOWED", 0x0006)`

8.12.1 Detailed Description

Definition at line 482 of file `__init__.py`.

The documentation for this class was generated from the following file:

- `linelidarclass/__init__.py`

8.13 macaddress Class Reference

Public Member Functions

- `None` `__init__` (`macaddress` self, `Union[str, bytes]` addr)
- `bool` `__eq__` (`macaddress` self, `object` other)
- `str` `__repr__` (`macaddress` self)

Public Attributes

- [mac](#)

8.13.1 Detailed Description

Definition at line 96 of file `__init__.py`.

The documentation for this class was generated from the following file:

- `linelidarclass/__init__.py`

Index

- [_LLchr](#), [15](#)
 - [__eq__](#), [16](#)
 - [__hash__](#), [16](#)
 - [__init__](#), [15](#)
 - [__setattr__](#), [16](#)
- [_LLcmd](#), [17](#)
- [_LLintEnum](#), [18](#)
 - [__eq__](#), [19](#)
 - [__hash__](#), [19](#)
 - [__init__](#), [18](#)
 - [__setattr__](#), [19](#)
- [_LLsrv](#), [20](#)
- [_LLsta](#), [21](#)
- [__decode_msg](#)
 - [LineLidar](#), [25](#)
- [__encode_cmd](#)
 - [LineLidar](#), [25](#)
- [__eq__](#)
 - [_LLchr](#), [16](#)
 - [_LLintEnum](#), [19](#)
- [__hash__](#)
 - [_LLchr](#), [16](#)
 - [_LLintEnum](#), [19](#)
- [__highlighted_bytes](#)
 - [LineLidar](#), [26](#)
- [__init__](#)
 - [_LLchr](#), [15](#)
 - [_LLintEnum](#), [18](#)
 - [LineLidar](#), [24](#)
- [__recv_ssh_line](#)
 - [LineLidar](#), [26](#)
- [__repr__](#)
 - [LLresponse](#), [47](#)
- [__retry_cmd](#)
 - [LineLidar](#), [27](#)
- [__setattr__](#)
 - [_LLchr](#), [16](#)
 - [_LLintEnum](#), [19](#)
- [__windows_reader_thread](#)
 - [LineLidar](#), [27](#)
- [_get_cmd_response](#)
 - [LineLidar](#), [27](#)
- [_recv_msg](#)
 - [LineLidar](#), [28](#)
- [_send_cmd](#)
 - [LineLidar](#), [30](#)
- [_send_data](#)
 - [LineLidar](#), [30](#)
- [AMPLITUDE_THRESHOLD](#)
 - [LLchr](#), [40](#)
- [Base classes](#), [11](#)
- [CALIBRATED_ANGLES](#)
 - [LLchr](#), [40](#)
- [Default parameters](#), [11](#)
- [DEFAULT_NETWORK](#)
 - [LLchr](#), [41](#)
- [disable_all_notifications](#)
 - [LineLidar](#), [31](#)
- [disable_notification](#)
 - [LineLidar](#), [31](#)
- [discover](#)
 - [linelidarclass.linelidar](#), [14](#)
- [enable_notification](#)
 - [LineLidar](#), [32](#)
- [Enums](#), [11](#)
- [FW_VERSION](#)
 - [LLchr](#), [41](#)
- [get_notification](#)
 - [LineLidar](#), [32](#)
- [int](#)
 - [LineLidar](#), [39](#)
- [ipaddress](#), [21](#)
- [LineLidar](#), [22](#)
 - [__decode_msg](#), [25](#)
 - [__encode_cmd](#), [25](#)
 - [__highlighted_bytes](#), [26](#)
 - [__init__](#), [24](#)
 - [__recv_ssh_line](#), [26](#)
 - [__retry_cmd](#), [27](#)
 - [__windows_reader_thread](#), [27](#)
 - [_get_cmd_response](#), [27](#)
 - [_recv_msg](#), [28](#)
 - [_send_cmd](#), [30](#)
 - [_send_data](#), [30](#)
 - [disable_all_notifications](#), [31](#)
 - [disable_notification](#), [31](#)
 - [enable_notification](#), [32](#)
 - [get_notification](#), [32](#)
 - [int](#), [39](#)
 - [open](#), [33](#)
 - [read_chr](#), [34](#)
 - [report_zero_results](#), [34](#)

- reset, [35](#)
- restore_srv, [35](#)
- save_srv, [36](#)
- set_clean_state, [36](#)
- set_notification, [37](#)
- set_sampling_rate, [37](#)
- stop_sampling, [38](#)
- wait_device_quiet, [38](#)
- write_chr, [39](#)
- linelidarclass, [13](#)
- linelidarclass.default, [13](#)
- linelidarclass.linelidar, [14](#)
 - discover, [14](#)
- LLchr, [40](#)
 - AMPLITUDE_THRESHOLD, [40](#)
 - CALIBRATED_ANGLES, [40](#)
 - DEFAULT_NETWORK, [41](#)
 - FW_VERSION, [41](#)
 - MAC, [41](#)
 - MAX_ANGLE, [41](#)
 - MAX_DISTANCE, [42](#)
 - MEASURING_RATE, [42](#)
 - MIN_ANGLE, [42](#)
 - MIN_DISTANCE, [42](#)
 - NB_PEAKS, [43](#)
 - NETWORK, [43](#)
 - RANGE, [43](#)
 - REPORT_ZERO_RESULTS, [43](#)
 - RESET_DEVICE, [44](#)
 - SERIAL_NUMBER, [44](#)
 - TEMPERATURE, [44](#)
 - TIME, [44](#)
 - TRIGGER_DIVISION, [45](#)
 - TRIGGER_SOURCE, [45](#)
 - TRIGGER_TYPE, [45](#)
- LLcmd, [46](#)
- LLresponse, [46](#)
 - __repr__, [47](#)
 - reset, [47](#)
- LLsrv, [48](#)
- LLsta, [48](#)
- MAC
 - LLchr, [41](#)
- macaddress, [48](#)
- Main classes, [11](#)
- MAX_ANGLE
 - LLchr, [41](#)
- MAX_DISTANCE
 - LLchr, [42](#)
- MEASURING_RATE
 - LLchr, [42](#)
- MIN_ANGLE
 - LLchr, [42](#)
- MIN_DISTANCE
 - LLchr, [42](#)
- NB_PEAKS
 - LLchr, [43](#)
- NETWORK
 - LLchr, [43](#)
- open
 - LineLidar, [33](#)
- RANGE
 - LLchr, [43](#)
- read_chr
 - LineLidar, [34](#)
- REPORT_ZERO_RESULTS
 - LLchr, [43](#)
- report_zero_results
 - LineLidar, [34](#)
- reset
 - LineLidar, [35](#)
 - LLresponse, [47](#)
- RESET_DEVICE
 - LLchr, [44](#)
- restore_srv
 - LineLidar, [35](#)
- Routines, [11](#)
- save_srv
 - LineLidar, [36](#)
- SERIAL_NUMBER
 - LLchr, [44](#)
- set_clean_state
 - LineLidar, [36](#)
- set_notification
 - LineLidar, [37](#)
- set_sampling_rate
 - LineLidar, [37](#)
- stop_sampling
 - LineLidar, [38](#)
- TEMPERATURE
 - LLchr, [44](#)
- TIME
 - LLchr, [44](#)
- TRIGGER_DIVISION
 - LLchr, [45](#)
- TRIGGER_SOURCE
 - LLchr, [45](#)
- TRIGGER_TYPE
 - LLchr, [45](#)
- wait_device_quiet
 - LineLidar, [38](#)
- write_chr
 - LineLidar, [39](#)